

4.3. SYMBOLS FOR SPACE GROUPS

Examples

- (1) $P4_2/mbc$ (135). From the full symbol, the first maximal t subgroup is found to be $P2_1/b\ 2_1/a\ 2/m$ ($Pbam$). The C -cell symbol is $C4_2/m\ cg_1$ and gives rise to the second maximal orthorhombic t subgroup $Cccm$, cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$.
- (2) $I4/m\ cm$ (140). Similarly, the first orthorhombic maximal t subgroup is $Iccm$ ($Ibam$); the second maximal orthorhombic t subgroup is obtained from the F -cell symbol as $Fc\ c\ m$ ($Fmmm$), cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$.

These examples show that P - and C -cell, as well as I - and F -cell descriptions of tetragonal groups have to be considered together.

(iii) Monoclinic subgroups

Only space groups of classes 4, $\bar{4}$ and $4/m$ have maximal monoclinic t subgroups.

Examples

- (1) $P4_1$ (76) has the subgroup $P112_1$ ($P2_1$). The C -cell description does not add new features: $C112_1$ is reducible to $P2_1$.
- (2) $I4_1/a$ (88) has the subgroup $I112_1/a$, equivalent to $I112/a$ ($C2/c$). The F -cell description yields the same subgroup $F11\ 2/d$, again reducible to $C2/c$.

4.3.5. Trigonal and hexagonal systems

The trigonal and hexagonal crystal systems are considered together, because they form the hexagonal 'crystal family', as explained in Chapter 2.1. Hexagonal lattices occur in both systems, whereas rhombohedral lattices occur only in the trigonal system.

4.3.5.1. Historical note

The 1935 edition of *International Tables* contains the symbols C and H for the hexagonal lattice and R for the rhombohedral lattice. C recalls that the hexagonal lattice can be described by a double rectangular C -centred cell (orthohexagonal axes); H was used for a hexagonal triple cell (see below); R designates the rhombohedral lattice and is used for both the rhombohedral description (primitive cell) and the hexagonal description (triple cell).

In the 1952 edition the following changes took place (*cf.* pages x, 51 and 544 of *IT* 1952): The lattice symbol C was replaced by P for reasons of consistency; the H description was dropped. The symbol R was kept for both descriptions, rhombohedral and hexagonal. The tertiary symmetry element in the short Hermann–Mauguin symbols of class 622, which was omitted in *IT* (1935), was re-established.

In the present volume, the use of P and R is the same as in *IT* (1952). The H cell, however, reappears in the sub- and supergroup data of Part 7 and in Table 4.3.2.1 of this section, where short symbols for the H description of trigonal and hexagonal space groups are given. The C cell reappears in the subgroup data for all trigonal and hexagonal space groups having symmetry elements orthogonal to the main axis.

4.3.5.2. Primitive cells

The primitive cells of the hexagonal and the rhombohedral lattice, hP and hR , are defined in Table 2.1.2.1 In Part 7, the 'rhombohedral' description of the hR lattice is designated by 'rhombohedral axes'; *cf.* Chapter 1.2.

4.3.5.3. Multiple cells

Multiple cells are frequently used to describe both the hexagonal and the rhombohedral lattice.

(i) The triple hexagonal R cell; *cf.* Chapters 1.2 and 2.1

When the lattice is rhombohedral hR (primitive cell $\mathbf{a}, \mathbf{b}, \mathbf{c}$), the triple R cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$ corresponds to the 'hexagonal description' of the rhombohedral lattice. There are three right-handed *obverse* R cells:

$$\begin{aligned} R_1: & \mathbf{a}' = \mathbf{a} - \mathbf{b}; & \mathbf{b}' = \mathbf{b} - \mathbf{c}; & \mathbf{c}' = \mathbf{a} + \mathbf{b} + \mathbf{c}; \\ R_2: & \mathbf{a}' = \mathbf{b} - \mathbf{c}; & \mathbf{b}' = \mathbf{c} - \mathbf{a}; & \mathbf{c}' = \mathbf{a} + \mathbf{b} + \mathbf{c}; \\ R_3: & \mathbf{a}' = \mathbf{c} - \mathbf{a}; & \mathbf{b}' = \mathbf{a} - \mathbf{b}; & \mathbf{c}' = \mathbf{a} + \mathbf{b} + \mathbf{c}. \end{aligned}$$

Three further right-handed R cells are obtained by changing \mathbf{a}' and \mathbf{b}' to $-\mathbf{a}'$ and $-\mathbf{b}'$, *i.e.* by a 180° rotation around \mathbf{c}' . These cells are *reverse*. The transformations between the triple R cells and the primitive rhombohedral cell are given in Table 5.1.3.1 and Fig. 5.1.3.6.

The *obverse* triple R cell has 'centring points' at

$$0, 0, 0; \quad \frac{2}{3}, \frac{1}{3}, \frac{1}{3}; \quad \frac{1}{3}, \frac{2}{3}, \frac{2}{3},$$

whereas the *reverse* R cell has 'centring points' at

$$0, 0, 0; \quad \frac{1}{3}, \frac{2}{3}, \frac{1}{3}; \quad \frac{2}{3}, \frac{1}{3}, \frac{2}{3}.$$

In the space-group tables of Part 7, the *obverse* R_1 cell is used, as illustrated in Fig. 2.2.6.9. This 'hexagonal description' is designated by 'hexagonal axes'.

(ii) The triple rhombohedral D cell

Parallel to the hexagonal description of the rhombohedral lattice there exists a 'rhombohedral description of the hexagonal lattice'. Six right-handed rhombohedral cells (here denoted by D) with cell vectors $\mathbf{a}', \mathbf{b}', \mathbf{c}'$ of equal lengths are obtained from the hexagonal P cell $\mathbf{a}, \mathbf{b}, \mathbf{c}$ by the following transformations and by cyclic permutations of $\mathbf{a}', \mathbf{b}', \mathbf{c}'$:

$$\begin{aligned} D_1: & \mathbf{a}' = \mathbf{a} + \mathbf{c}; & \mathbf{b}' = \mathbf{b} + \mathbf{c}; & \mathbf{c}' = -(\mathbf{a} + \mathbf{b}) + \mathbf{c} \\ D_2: & \mathbf{a}' = -\mathbf{a} + \mathbf{c}; & \mathbf{b}' = -\mathbf{b} + \mathbf{c}; & \mathbf{c}' = \mathbf{a} + \mathbf{b} + \mathbf{c}. \end{aligned}$$

The transformation matrices are listed in Table 5.1.3.1. D_2 follows from D_1 by a 180° rotation around $[111]$. The D cells are triple rhombohedral cells with 'centring' points at

$$0, 0, 0; \quad \frac{1}{3}, \frac{1}{3}, \frac{1}{3}; \quad \frac{2}{3}, \frac{2}{3}, \frac{2}{3}.$$

The D cell, not used in practice and not considered explicitly in the present volume, is useful for a deeper understanding of the relations between hexagonal and rhombohedral lattices.

(iii) The triple hexagonal H cell; *cf.* Chapter 1.2

Generally, a hexagonal lattice hP is described by means of the smallest hexagonal P cell. An alternative description employs a larger hexagonal H -centred cell of three times the volume of the P cell; this cell was extensively used in *IT* (1935), see *Historical note* above.

There are three right-handed orientations of the H cell (basis vectors $\mathbf{a}', \mathbf{b}', \mathbf{c}'$) with respect to the basis vectors $\mathbf{a}, \mathbf{b}, \mathbf{c}$ of the P cell:

$$\begin{aligned} H_1: & \mathbf{a}' = \mathbf{a} - \mathbf{b}; & \mathbf{b}' = \mathbf{a} + 2\mathbf{b}; & \mathbf{c}' = \mathbf{c} \\ H_2: & \mathbf{a}' = 2\mathbf{a} + \mathbf{b}; & \mathbf{b}' = -\mathbf{a} + \mathbf{b}; & \mathbf{c}' = \mathbf{c} \\ H_3: & \mathbf{a}' = \mathbf{a} + 2\mathbf{b}; & \mathbf{b}' = -2\mathbf{a} - \mathbf{b}; & \mathbf{c}' = \mathbf{c}. \end{aligned}$$

The transformations are given in Table 5.1.3.1 and Fig. 5.1.3.8. The new vectors \mathbf{a}' and \mathbf{b}' are rotated in the ab plane by -30° (H_1), $+30^\circ$ (H_2), $+90^\circ$ (H_3) with respect to the old vectors \mathbf{a} and \mathbf{b} . Three further right-handed H cells are obtained by changing \mathbf{a}' and \mathbf{b}' to $-\mathbf{a}'$ and $-\mathbf{b}'$, *i.e.* by a rotation of 180° around \mathbf{c}' .

The H cell has 'centring' points at

$$0, 0, 0; \quad \frac{2}{3}, \frac{1}{3}, 0; \quad \frac{1}{3}, \frac{2}{3}, 0.$$

4. SYNOPTIC TABLES OF SPACE-GROUP SYMBOLS

Secondary and tertiary symmetry elements of the P cell are interchanged in the H cell, and the general position in the H cell is easily obtained, as illustrated by the following example.

Example

The space-group symbol $P3m1$ in the P cell $\mathbf{a}, \mathbf{b}, \mathbf{c}$ becomes $H31m$ in the H cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$. To obtain the general position of $H31m$, consider the coordinate triplets of $P31m$ and add the centring translations $0, 0, 0; \frac{2}{3}, \frac{1}{3}, 0; \frac{1}{3}, \frac{2}{3}, 0$.

(iv) The double orthohexagonal C cell

The C -centred cell which is defined by the so-called 'orthohexagonal' vectors $\mathbf{a}', \mathbf{b}', \mathbf{c}'$ has twice the volume of the P cell. There are six right-handed orientations of the C cell, which are C_1, C_2 and C_3 plus three further ones obtained by changing \mathbf{a}' and \mathbf{b}' to $-\mathbf{a}'$ and $-\mathbf{b}'$:

$$\begin{aligned} C_1 : \mathbf{a}' = \mathbf{a} & ; \mathbf{b}' = \mathbf{a} + 2\mathbf{b} & ; \mathbf{c}' = \mathbf{c} \\ C_2 : \mathbf{a}' = \mathbf{a} + \mathbf{b} & ; \mathbf{b}' = -\mathbf{a} + \mathbf{b} & ; \mathbf{c}' = \mathbf{c} \\ C_3 : \mathbf{a}' = \mathbf{b} & ; \mathbf{b}' = -2\mathbf{a} - \mathbf{b} & ; \mathbf{c}' = \mathbf{c} \end{aligned}$$

Transformation matrices are given in Table 5.1.3.1 and illustrations in Fig. 5.1.3.7. Here \mathbf{b}' is the long axis.

4.3.5.4. Relations between symmetry elements

In the hexagonal crystal classes $62(2)$, $6m(m)$ and $\bar{6}2(m)$ or $\bar{6}m(2)$, where the tertiary symmetry element is between parentheses, the following products hold:

$$6 \times 2 = (2) = \bar{6} \times m; \quad 6 \times m = (m) = \bar{6} \times 2$$

or

$$6 \times 2 \times (2) = 6 \times m \times (m) = \bar{6} \times 2 \times (m) = \bar{6} \times m \times (2) = 1.$$

The same relations hold for the corresponding Hermann–Mauguin space-group symbols.

4.3.5.5. Additional symmetry elements

Parallel axes 2 and 2_1 occur perpendicular to the principal symmetry axis. Examples are space groups $R32$ (155), $P321$ (150) and $P312$ (149), where the screw components are $\frac{1}{2}, \frac{1}{2}, 0$ (rhombohedral axes) or $\frac{1}{2}, 0, 0$ (hexagonal axes) for $R32$; $\frac{1}{2}, 0, 0$ for $P321$; and $\frac{1}{2}, 1, 0$ for $P312$. Hexagonal examples are $P622$ (177) and $P62c$ (190).

Likewise, mirror planes m parallel to the main symmetry axis alternate with glide planes, the glide components being perpendicular to the principal axis. Examples are $P3m1$ (156), $P31m$ (157), $R3m$ (160) and $P6mm$ (183).

Glide planes c parallel to the main axis are interleaved by glide planes n . Examples are $P3c1$ (158), $P31c$ (159), $R3c$ (161, hexagonal axes), $P6c2$ (188). In $R3c$ and $R\bar{3}c$, the glide component $0, 0, \frac{1}{2}$ for hexagonal axes becomes $\frac{1}{2}, \frac{1}{2}, \frac{1}{2}$ for rhombohedral axes, i.e. the c glide changes to an n glide. Thus, if the space group is referred to rhombohedral axes, diagonal n planes alternate with diagonal a, b or c planes (cf. Section 1.4.4).

In R space groups, all additional symmetry elements with glide and screw components have their origin in the action of an integral lattice translation. This is also true for the axes 3_1 and 3_2 which appear in all R space groups (cf. Table 4.1.2.2). For this reason, the 'rhombohedral centring' R is not included in Table 4.1.2.3, which contains only the centring A, B, C, I, F .

4.3.5.6. Group-subgroup relations

4.3.5.6.1. Maximal k subgroups

Maximal k subgroups of index [3] are obtained by 'decentring' the triple cells R (hexagonal description), D and H in the trigonal

system, H in the hexagonal system. Any one of the three centring points may be taken as origin of the subgroup.

(i) Trigonal system

Examples

(1) $P3m1$ (156) (cell $\mathbf{a}, \mathbf{b}, \mathbf{c}$) is equivalent to $H31m$ ($\mathbf{a}', \mathbf{b}', \mathbf{c}'$). Decentring of the H cell yields maximal non-isomorphic k subgroups of type $P31m$. Similarly, $P31m$ (157) has maximal subgroups of type $P3m1$; thus, one can construct infinite chains of subgroup relations of index [3], tripling the cell at each step:

$$P3m1 \rightarrow P31m \rightarrow P3m1 \dots$$

(2) $R3$ (146), by decentring the triple hexagonal R cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$, yields the subgroups $P3, P3_1$ and $P3_2$ of index [3].

(3) Likewise, decentring of the triple rhombohedral cells D_1 and D_2 gives rise, for each cell, to the rhombohedral subgroups of a trigonal P group, again of index [3].

Combining (2) and (3), one may construct infinite chains of subgroup relations, tripling the cell at each step:

$$P3 \rightarrow R3 \rightarrow P3 \rightarrow R3 \dots$$

These chains illustrate best the connections between rhombohedral and hexagonal lattices.

(4) Special care must be applied when secondary or tertiary symmetry elements are present. Combining (1), (2) and (3), one has for instance:

$$P31c \rightarrow R3c \rightarrow P3c1 \rightarrow P31c \rightarrow R3c \dots$$

(5) Rhombohedral subgroups, found by decentring the triple cells D_1 and D_2 , are given under block **IIIb** and are referred there to hexagonal axes, $\mathbf{a}', \mathbf{b}', \mathbf{c}'$ as listed below. Examples are space groups $P3$ (143) and $P\bar{3}1c$ (163)

$$\begin{aligned} \mathbf{a}' = \mathbf{a} - \mathbf{b}, \quad \mathbf{b}' = \mathbf{a} + 2\mathbf{b}, \quad \mathbf{c}' = 3\mathbf{c}; \\ \mathbf{a}' = 2\mathbf{a} + \mathbf{b}, \quad \mathbf{b}' = -\mathbf{a} + \mathbf{b}, \quad \mathbf{c}' = 3\mathbf{c}. \end{aligned}$$

(ii) Hexagonal system

Examples

(1) $P62c$ (190) is described as $H\bar{6}c2$ in the triple cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$; decentring yields the non-isomorphic subgroup $P\bar{6}c2$.

(2) $P6/mcc$ (192) (cell $\mathbf{a}, \mathbf{b}, \mathbf{c}$) keeps the same symbol in the H cell and, consequently, gives rise to the maximal isomorphic subgroup $P6/mcc$ with cell $\mathbf{a}', \mathbf{b}', \mathbf{c}'$. An analogous result applies whenever secondary and tertiary symmetry elements in the Hermann–Mauguin symbol are the same and also to space groups of classes $6, \bar{6}$ and $6/m$.

4.3.5.6.2. Maximal t subgroups

Maximal t subgroups of index [2] are read directly from the full symbol of the space groups of classes $32, 3m, \bar{3}m, 622, 6mm, \bar{6}2m, 6/mmm$.

Maximal t subgroups of index [3] follow from the third power of the main-axis operation. Here the C -cell description is valuable.

(i) Trigonal system

(a) Trigonal subgroups

Examples

(1) $R\bar{3}2/c$ (167) has $R3c, R32$ and $R\bar{3}$ as maximal t subgroups of index [2].

(2) $P\bar{3}c1$ (165) has $P3c1, P321$ and $P\bar{3}$ as maximal t subgroups of index [2].